



Essential Personnel Only!

Full Barrier Isolation Required

Personal Protective Equipment (PPE) Placement

Before ENTERING Negative Air Space

STEP 1 Put on fluid-resistant gown

Insert thumb into thumb hole, if present. Tie securely in back.



STEP 2 Put on shoe covers



STEP 3 Put on N95 respirator

Shape nosepiece to the nose with both index fingers. Place top band on top of head. Place lower band just above neck.



STEP 4 Fit-check/seal-check respirator

Place both hands over respirator. Exhale sharply. If air-leaks are detected, re-adjust respirator; exhale sharply again. If leak still present, seek assistance.



STEP 5 Put on headcover

Contain hair and cover ears.



STEP 6 Put on face shield

Fully cover the face and forehead.



STEP 7 Put on gloves

Pull gloves over sleeves to cover wrist.



Change gloves:

- when damaged or heavily contaminated
- between procedures

After ENTERING Negative Air Space

After entering patient room, keep gloved hands away from face and avoid unnecessary touching of objects or surfaces.

Personal Protective Equipment (PPE) Removal

Before LEAVING Negative Air Space

Note: Discard used items in red bag.

STEP 1 Faceshield

Remove and discard.



STEP 2 Headcover

Remove and discard.



STEP 3 Shoe covers

Remove and discard.



STEP 4 Gown & gloves

Grasp shoulders of gown and pull forward. Roll outside of gown inward, folding contaminated outside layer away from your body.



Remove gloves while rolling gown off arms; roll gloves into gown. Avoid contaminating hands. Keep hands on clean side of gown. Discard gown and gloves.



STEP 5 Hand hygiene

Clean hands with antimicrobial soap and water or alcohol-based hand rub.



LEAVE Negative Air Space, CLOSE Door

STEP 6 N95 respirator

Front of respirator is contaminated. Handle only the bands. To remove, pull lower band over the head first, then remove upper band. Discard.



STEP 7 Hand hygiene

Clean hands with antimicrobial soap and water or alcohol-based hand rub.



Note: If Powered Air Purifying Respirator (PAPR) is used, follow facility procedures for applying, removing, and processing equipment. PAPR or tight-fitting goggles should be worn for high-risk aerosol-generating procedures.